

# DVD CAM Software Support Center

---

## *DVD-MovieAlbum SE Version 3.0 L60 Updater* *English Version*

---


### Released

July 2003

### Versions to Update

This updater applies to the following versions of the DVD-MovieAlbumSE bundled with the DVDCAM:

- DVD-MovieAlbumSE Version 3.0 L23
- DVD-MovieAlbumSE Version 3.0 L23A
- DVD-MovieAlbumSE Version 3.0 L23B

To check your version, start DVD-MovieAlbumSE, and then click the Help button  on the top right of the screen, followed by **About DVD-MovieAlbum**.

### Improvements

- 1) Supports capture of AVI file images created by Windows MovieMaker2.
- 2) Fixes the following problems.
  - Approximately one minute is taken to automatically view DVD-RAM content thumbnails when DVD-MovieAlbum is activated.
  - DVD-MovieAlbum aborts when a 3D-title is input to a program that is recorded within a second.
  - The picture quality of a zoomed in/out picture may deteriorate when images in AVI files are captured.
  - The disc may not be able to play back when a program is divided after a part of movies is deleted by a DVD recorder.
  - An error message "An unknown error occurred" may appear when still pictures (JPEG and BMP) are captured.
  - Pictures recorded with a DVD recorder may not be exported in the high-speed mode (Simple Export Mode).
  - The sound output mode cannot be changed when pictures recorded in the AC3 stereo sound are play backed.
  - A green line may appear on the right of the screen when images in AVI files are captured.
  - PC shutdown may slow down after DVD-MovieAlbumSE is repeatedly started in certain environments.

### Update Instructions

1. Download **DVD-MA3UpdateL60en.exe**.
2. Select and right-click the downloaded file in Windows Explorer or My Computer and click **Properties** to display the file information.
3. Check that the size of the downloaded file is 6,613,496 bytes.
4. Close all programs running on Windows. If DVD-MovieAlbum is running, close it.
5. Double-click the downloaded file to start the update. Install the updater by following the instructions of the update installer.